

# VRTRIX Data Glove Unity SDK Reference

Generated by Doxygen 1.8.16



<b>1 Namespace Index</b>	<b>1</b>
1.1 Packages	1
<b>2 Hierarchical Index</b>	<b>3</b>
2.1 Class Hierarchy	3
<b>3 Class Index</b>	<b>5</b>
3.1 Class List	5
<b>4 Namespace Documentation</b>	<b>7</b>
4.1 VRTRIX Namespace Reference	7
4.1.1 Enumeration Type Documentation	8
4.1.1.1 GloveIndex	8
4.1.1.2 GLOVEVERSION	8
4.1.1.3 HANDTYPE	8
4.1.1.4 VRTRIXBones	8
4.1.1.5 VRTRIXGloveEvent	9
4.1.1.6 VRTRIXGloveStatus	9
<b>5 Class Documentation</b>	<b>11</b>
5.1 VRTRIX.VRTRIXDataWrapper.VRTRIX_Quat Struct Reference	11
5.1.1 Detailed Description	11
5.2 VRTRIXBoneMapping Class Reference	11
5.2.1 Detailed Description	12
5.2.2 Member Function Documentation	12
5.2.2.1 MapToVRTRIX_BoneName()	12
5.3 VRTRIX.VRTRIXDataWrapper Class Reference	12
5.3.1 Detailed Description	14
5.3.2 Constructor & Destructor Documentation	15
5.3.2.1 VRTRIXDataWrapper()	15
5.3.3 Member Function Documentation	15
5.3.3.1 ChannelHopping()	15
5.3.3.2 ClosePort() [1/2]	15
5.3.3.3 ClosePort() [2/2]	16
5.3.3.4 GetReceiveBattery()	16
5.3.3.5 GetReceivedCalScore()	16
5.3.3.6 GetReceivedCalScoreMean()	17
5.3.3.7 GetReceivedDataRate()	17
5.3.3.8 GetReceivedGestureAngle()	17
5.3.3.9 GetReceivedRotation()	17
5.3.3.10 GetReceivedStatus()	18
5.3.3.11 GetReceiveRadioChannel()	18
5.3.3.12 GetReceiveRadioStrength()	18
5.3.3.13 Init()	18

5.3.3.14 InitDataGlove()	19
5.3.3.15 OnCloseFingerAlignment() [1/2]	19
5.3.3.16 OnCloseFingerAlignment() [2/2]	19
5.3.3.17 OnOkPoseAlignment()	21
5.3.3.18 OnSaveCalibration()	21
5.3.3.19 OpenPort()	21
5.3.3.20 ReceivedDataCallback()	22
5.3.3.21 ReceivedEventCallback()	22
5.3.3.22 RegisterDataCallback()	23
5.3.3.23 RegisterEventCallback()	23
5.3.3.24 SetAdvancedMode() [1/2]	23
5.3.3.25 SetAdvancedMode() [2/2]	23
5.3.3.26 SetDistalThumbOffset()	24
5.3.3.27 SetIntermediateThumbOffset()	24
5.3.3.28 SetProximalThumbOffset()	25
5.3.3.29 SetThumbOffset()	25
5.3.3.30 SetThumbSlerpRate() [1/2]	25
5.3.3.31 SetThumbSlerpRate() [2/2]	26
5.3.3.32 StartStreaming()	26
5.3.3.33 VibratePeriod() [1/2]	26
5.3.3.34 VibratePeriod() [2/2]	27
5.4 VRTRIX.VRTRIXGloveDataStreaming Class Reference	27
5.4.1 Detailed Description	29
5.4.2 Member Function Documentation	29
5.4.2.1 CheckDeviceModelName()	29
5.4.2.2 GetBatteryLevel()	30
5.4.2.3 GetCalScore()	30
5.4.2.4 GetGesture()	30
5.4.2.5 GetGloveConnectionStat()	31
5.4.2.6 GetReceivedCalScoreMean()	31
5.4.2.7 GetReceivedDataRate()	32
5.4.2.8 GetReceivedStatus()	32
5.4.2.9 GetReceiveRadioChannel()	32
5.4.2.10 GetReceiveRadioStrength()	33
5.4.2.11 GetRotation()	33
5.4.2.12 SetAdvancedMode()	33
5.5 VRTRIX.VRTRIXUtilities Class Reference	34
5.5.1 Detailed Description	34
5.5.2 Member Function Documentation	34
5.5.2.1 GetBoneIndex()	34
5.5.2.2 GetBoneName()	35





# Chapter 1

## Namespace Index

### 1.1 Packages

Here are the packages with brief descriptions (if available):

VRTRIX . . . . .	7
------------------	---





## Chapter 2

# Hierarchical Index

### 2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

MonoBehaviour	
VRTRIX.VRTRIXGloveDataStreaming . . . . .	<a href="#">27</a>
VRTRIXBoneMapping . . . . .	<a href="#">11</a>
VRTRIX.VRTRIXDataWrapper.VRTRIX_Quat . . . . .	<a href="#">11</a>
VRTRIX.VRTRIXDataWrapper . . . . .	<a href="#">12</a>
VRTRIX.VRTRIXUtilities . . . . .	<a href="#">34</a>



## Chapter 3

# Class Index

### 3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<a href="#">VRTRIX.VRTRIXDataWrapper.VRTRIX_Quat</a>	
Quaternion data struction used in unmanaged C++ API . . . . .	11
<a href="#">VRTRIXBoneMapping</a>	
Bone mapping class . . . . .	11
<a href="#">VRTRIX.VRTRIXDataWrapper</a>	
<a href="#">VRTRIX</a> Data Glove data wrapper class . . . . .	12
<a href="#">VRTRIX.VRTRIXGloveDataStreaming</a>	
<a href="#">VRTRIX</a> Data Glove data streaming class . . . . .	27
<a href="#">VRTRIX.VRTRIXUtilities</a>	
Bone utility functions class . . . . .	34



## Chapter 4

# Namespace Documentation

### 4.1 VRTRIX Namespace Reference

#### Classes

- class [VRTRIXDataWrapper](#)  
*VRTRIX Data Glove data wrapper class.*
- class [VRTRIXGloveDataStreaming](#)  
*VRTRIX Data Glove data streaming class.*
- class [VRTRIXUtilities](#)  
*Bone utility functions class.*

#### Enumerations

- enum [GloveIndex](#) {  
**None** = -1, **Device0** = 0, **Device1** = 1, **Device2** = 2,  
**Device3** = 3, **Device4** = 4, **Device5** = 5, **Device6** = 6,  
**Device7** = 7, **Device8** = 8, **Device9** = 9, **Device10** = 10,  
**Device11** = 11, **Device12** = 12, **Device13** = 13, **Device14** = 14,  
**Device15** = 15, **MaxDeviceCount** = 16 }  
*GloveIndex enum.*
- enum [HANDTYPE](#) { **RIGHT\_HAND**, **LEFT\_HAND**, **BOTH\_HAND**, **NONE** }  
*Hand type enum.*
- enum [GLOVEVERSION](#) { **DK1**, **DK2**, **PRO** }  
*Glove hardware version.*
- enum [VRTRIXGloveStatus](#) {  
**CLOSED**, **NORMAL**, **PAUSED**, **DISCONNECTED**,  
**MAGANOMALY** }  
*Glove connection status.*
- enum [VRTRIXGloveEvent](#) {  
**VRTRIXGloveEvent\_None** = 0, **VRTRIXGloveEvent\_Idle** = 1, **VRTRIXGloveEvent\_Connected** = 2, **VRTRIXGloveEvent\_Disconnected** = 3,  
**VRTRIXGloveEvent\_PortClosed** = 4, **VRTRIXGloveEvent\_LowBattery** = 5, **VRTRIXGloveEvent\_BatteryFull** = 6, **VRTRIXGloveEvent\_Paired** = 7,  
**VRTRIXGloveEvent\_MagAbnormal** = 8, **VRTRIXGloveEvent\_TrackerConnected** = 9, **VRTRIXGloveEvent\_TrackerDisconnected** = 10, **VRTRIXGloveEvent\_ChannelHopping** = 11 }  
*Glove event enum.*

- enum [VRTRIXBones](#) {  
**R\_Hand** = 0, **R\_Thumb\_1** = 1, **R\_Thumb\_2** = 2, **R\_Thumb\_3** = 3,  
**R\_Index\_1** = 4, **R\_Index\_2** = 5, **R\_Index\_3** = 6, **R\_Middle\_1** = 7,  
**R\_Middle\_2** = 8, **R\_Middle\_3** = 9, **R\_Ring\_1** = 10, **R\_Ring\_2** = 11,  
**R\_Ring\_3** = 12, **R\_Pinky\_1** = 13, **R\_Pinky\_2** = 14, **R\_Pinky\_3** = 15,  
**L\_Hand** = 16, **L\_Thumb\_1** = 17, **L\_Thumb\_2** = 18, **L\_Thumb\_3** = 19,  
**L\_Index\_1** = 20, **L\_Index\_2** = 21, **L\_Index\_3** = 22, **L\_Middle\_1** = 23,  
**L\_Middle\_2** = 24, **L\_Middle\_3** = 25, **L\_Ring\_1** = 26, **L\_Ring\_2** = 27,  
**L\_Ring\_3** = 28, **L\_Pinky\_1** = 29, **L\_Pinky\_2** = 30, **L\_Pinky\_3** = 31,  
**R\_Arm** = 32, **L\_Arm** = 33, **NumOfBones** = 34 }

*Hand joints enum.*

## 4.1.1 Enumeration Type Documentation

### 4.1.1.1 GloveIndex

```
enum VRTRIX.GloveIndex [strong]
```

GloveIndex enum.

Enum of supported gloves hardware index.

### 4.1.1.2 GLOVEVERSION

```
enum VRTRIX.GLOVEVERSION [strong]
```

Glove hardware version.

Supported hardware version, currently DK1, DK2 & PRO are supported.

### 4.1.1.3 HANDTYPE

```
enum VRTRIX.HANDTYPE [strong]
```

Hand type enum.

The chirality of the hand, used to identify data glove attribute.

### 4.1.1.4 VRTRIXBones

```
enum VRTRIX.VRTRIXBones [strong]
```

Hand joints enum.

Enum of joints for both hands.

#### 4.1.1.5 VRTRIXGloveEvent

```
enum VRTRIX.VRTRIXGloveEvent [strong]
```

Glove event enum.

Define the glove events while running.

#### 4.1.1.6 VRTRIXGloveStatus

```
enum VRTRIX.VRTRIXGloveStatus [strong]
```

Glove connection status.

Define the glove connection status.





## Chapter 5

# Class Documentation

### 5.1 VRTRIX.VRTRIXDataWrapper.VRTRIX\_Quat Struct Reference

Quaternion data struction used in unmanaged C++ API.

#### Public Attributes

- float [qx](#)  
*x component in quaternion*
- float [qy](#)  
*y component in quaternion*
- float [qz](#)  
*z component in quaternion*
- float [qw](#)  
*w component in quaternion*

#### 5.1.1 Detailed Description

Quaternion data struction used in unmanaged C++ API.


The documentation for this struct was generated from the following file:

- VRTRIXBasicDataStreaming/VRTRIXDataWrapper.cs

### 5.2 VRTRIXBoneMapping Class Reference

Bone mapping class.

Inheritance diagram for VRTRIXBoneMapping:



## Public Member Functions

- GameObject [MapToVRTRIX\\_BoneName](#) (string bone\_name)  
*Get custom model joint as gameobject according to bone name specified.*

## Public Attributes

- Transform[] **MyCharacterFingers** = new Transform[(int)VRTRIXBones.NumOfBones]

## Static Public Attributes

- static [VRTRIXBoneMapping](#) **UniqueStance**

### 5.2.1 Detailed Description

Bone mapping class.

A class to map bone names of custom model with [VRTRIX](#) bone setup.

### 5.2.2 Member Function Documentation

#### 5.2.2.1 MapToVRTRIX\_BoneName()

```
GameObject VRTRIXBoneMapping.MapToVRTRIX_BoneName (
    string bone_name )
```

Get custom model joint as gameobject according to bone name specified.

#### Parameters

<i>bone_name</i>	Given <a href="#">VRTRIX</a> bone name.
------------------	---

#### Returns

joint on the custom model as gameobject.

The documentation for this class was generated from the following file:

- VRTRIXBasicDataStreaming/VRTRIXBoneMapping.cs

## 5.3 VRTRIX.VRTRIXDataWrapper Class Reference

[VRTRIX](#) Data Glove data wrapper class.

## Classes

- struct [VRTRIX\\_Quat](#)  
*Quaternion data struction used in unmanaged C++ API.*

## Public Member Functions

- delegate void [ReceivedDataCallback](#) (IntPtr pUserParam, IntPtr ptr, int data\_rate, byte radio\_strength, IntPtr cal\_score\_ptr, float battery, int hand\_type, int radio\_channel)  
*The delegate data receive function called inside unmanaged C++ API.*
- delegate void [ReceivedEventCallback](#) (IntPtr pUserParam, IntPtr pEvent)  
*The delegate event receive function called inside unmanaged C++ API.*
- static IntPtr [InitDataGlove](#) (bool AdvancedMode, [GLOVEVERSION](#) HardwareVersion)  
*Intialize the data glove and returns the interface pointer.*
- static bool [OpenPort](#) (IntPtr sp, int glove\_id, [HANDTYPE](#) type)  
*Open the serial port*
- static void [StartStreaming](#) (IntPtr sp)  
*Read the data from serial port asynchronously.*
- static bool [ClosePort](#) (IntPtr sp)  
*Close the serial port*
- static void [OnSaveCalibration](#) (IntPtr sp)  
*Save calibration result to hardware*
- static void [OnCloseFingerAlignment](#) (IntPtr sp)  
*Align the close finger pose*
- static void [OnOkPoseAlignment](#) (IntPtr sp)  
*Align the OK finger pose*
- static void [RegisterDataCallback](#) (IntPtr pUserParam, IntPtr sp, [ReceivedDataCallback](#) receivedDataCallback)  
*Register receiving and parsed frame calculation data callback*
- static void [RegisterEventCallback](#) (IntPtr sp, [ReceivedEventCallback](#) receivedEventCallback)  
*Register receiving hardware event callback*
- static void [VibratePeriod](#) (IntPtr sp, int msDurationMillisec)  
*Vibrate the data glove for given time period.*
- static void [ChannelHopping](#) (IntPtr sp)  
*Randomly channel hopping.*
- static void [SetAdvancedMode](#) (IntPtr sp, bool blsAdvancedMode)  
*Set Advanced Mode.*
- static void [SetProximalThumbOffset](#) (IntPtr sp, double offset\_x, double offset\_y, double offset\_z)  
*Set Proximal Thumb Offset.*
- static void [SetIntermediateThumbOffset](#) (IntPtr sp, double offset\_x, double offset\_y, double offset\_z)  
*Set Intermediate Thumb Offset.*
- static void [SetDistalThumbOffset](#) (IntPtr sp, double offset\_x, double offset\_y, double offset\_z)  
*Set Distal Thumb Offset.*
- static void [SetThumbSlerpRate](#) (IntPtr sp, double slerp\_proximal, double slerp\_middle)  
*Set Thumb Slerp Rate.*
- [VRTRIXDataWrapper](#) (bool AdvancedMode, int [GloveIndex](#), [GLOVEVERSION](#) HardwareVersion)  
*Wrapper class construction method.*
- bool [Init](#) ([HANDTYPE](#) type)  
*Initialization method.*
- bool [ClosePort](#) ()

- Close port to stop data streaming.*

  - void [RegisterCallBack](#) ()

*Register call back function to the C++ unmanaged dll.*
- [VRTRIXGloveStatus](#) [GetReceivedStatus](#) ()

*Get data glove status.*
- float [GetReceivedGestureAngle](#) ([VRTRIXBones](#) bone)

*Get the angle between specific joint and wrist joint to detect gesture.*
- int [GetReceivedDataRate](#) ()

*Get data rate received per second.*
- int [GetReceiveRadioStrength](#) ()

*Get radio strength of data glove.*
- int [GetReceiveRadioChannel](#) ()

*Get current radio channel of data glove used.*
- float [GetReceiveBattery](#) ()

*Get current battery level in percentage of data glove.*
- int [GetReceivedCalScore](#) ([VRTRIXBones](#) bone)

*Get current calibration score for specific IMU sensor.*
- int [GetReceivedCalScoreMean](#) ()

*Get current calibration score average value.*
- Quaternion [GetReceivedRotation](#) ([VRTRIXBones](#) bone)

*Get current rotation for specific joint.*
- void [OnSaveCalibration](#) ()

*Save calibration parameters to hardware flash.*
- void [VibratePeriod](#) (int msDurationMillisec)

*Trigger a haptic vibration for a certain period.*
- void [OnCloseFingerAlignment](#) ([HANDTYPE](#) type)

*Align current gesture to finger close pose, used for calibration when advanced mode is activated.*
- void [StartStreaming](#) ()

*Start data streaming of data glove.*
- void [ChannelHopping](#) ()

*Trigger channel switching manually, only used in testing/debugging.*
- void [SetAdvancedMode](#) (bool blsAdvancedMode)

*Activate advanced mode so that finger's yaw data will be unlocked.*
- void [SetThumbOffset](#) (Vector3 offset, [VRTRIXBones](#) joint)

*Set thumb offset to counteract the difference between hands & gloves sensor installation.*
- void [SetThumbSlerpRate](#) (double slerp\_proximal, double slerp\_middle)

*Set thumb slerp rate to counteract the difference between hands & gloves sensor installation.*

## Static Public Attributes

- static [ReceivedDataCallback](#) **receivedDataCallback**
- static [ReceivedEventCallback](#) **receivedEventCallback**

### 5.3.1 Detailed Description

[VRTRIX](#) Data Glove data wrapper class.

A wrapper class to communicate with low-level unmanaged C++ API.

## 5.3.2 Constructor & Destructor Documentation

### 5.3.2.1 VRTRIXDataWrapper()

```
VRTRIX.VRTRIXDataWrapper.VRTRIXDataWrapper (
    bool AdvancedMode,
    int GloveIndex,
    GLOVEVERSION HardwareVersion )
```

Wrapper class construction method.

#### Parameters

<i>AdvancedMode</i>	Whether the advanced mode is activated
<i>GloveIndex</i>	Data glove index (Maximum is 15, if larger number is set, then only one pair of glove per PC is supported).
<i>HardwareVersion</i>	Data glove hardware version, currently DK1, DK2 and PRO are supported.

## 5.3.3 Member Function Documentation

### 5.3.3.1 ChannelHopping()

```
static void VRTRIX.VRTRIXDataWrapper.ChannelHopping (
    IntPtr sp )
```

Randomly channel hopping.

#### Parameters

<i>sp</i>	The serial port object
-----------	------------------------

### 5.3.3.2 ClosePort() [1/2]

```
bool VRTRIX.VRTRIXDataWrapper.ClosePort ( )
```

Close port to stop data streaming.

#### Returns

whether data streaming is stopped successfully.

### 5.3.3.3 ClosePort() [2/2]

```
static bool VRTRIX.VRTRIXDataWrapper.ClosePort (
    IntPtr sp )
```

Close the serial port

#### Parameters

<i>sp</i>	The serial port object
-----------	------------------------

#### Returns

Whether the serial port is closed successfully

### 5.3.3.4 GetReceiveBattery()

```
float VRTRIX.VRTRIXDataWrapper.GetReceiveBattery ( )
```

Get current battery level in percentage of data glove.

#### Returns

current battery level in percentage of data glove.

### 5.3.3.5 GetReceivedCalScore()

```
int VRTRIX.VRTRIXDataWrapper.GetReceivedCalScore (
    VRTRIXBones bone )
```

Get current calibration score for specific IMU sensor.

#### Parameters

<i>bone</i>	specific joint of hand.
-------------	-------------------------

#### Returns

current calibration score for specific IMU sensor. Lower value of score means better calibration performance.

#### 5.3.3.6 GetReceivedCalScoreMean()

```
int VRTRIX.VRTRIXDataWrapper.GetReceivedCalScoreMean ( )
```

Get current calibration score average value.

##### Returns

current calibration score average value.

#### 5.3.3.7 GetReceivedDataRate()

```
int VRTRIX.VRTRIXDataWrapper.GetReceivedDataRate ( )
```

Get data rate received per second.

##### Returns

data rate received per second.

#### 5.3.3.8 GetReceivedGestureAngle()

```
float VRTRIX.VRTRIXDataWrapper.GetReceivedGestureAngle (
    VRTRIXBones bone )
```

Get the angle between specific joint and wrist joint to detect gesture.

##### Parameters

<i>bone</i>	specific joint of hand.
-------------	-------------------------

##### Returns

the gesture angle for specific joint.

#### 5.3.3.9 GetReceivedRotation()

```
Quaternion VRTRIX.VRTRIXDataWrapper.GetReceivedRotation (
    VRTRIXBones bone )
```

Get current rotation for specific joint.

**Parameters**

<i>bone</i>	specific joint of hand.
-------------	-------------------------

**Returns**

current calibration score average value.

**5.3.3.10 GetReceivedStatus()**

```
VRTRIXGloveStatus VRTRIX.VRTRIXDataWrapper.GetReceivedStatus ( )
```

Get data glove status.

**Returns**

data glove status.

**5.3.3.11 GetReceiveRadioChannel()**

```
int VRTRIX.VRTRIXDataWrapper.GetReceiveRadioChannel ( )
```

Get current radio channel of data glove used.

**Returns**

current radio channel of data glove used.

**5.3.3.12 GetReceiveRadioStrength()**

```
int VRTRIX.VRTRIXDataWrapper.GetReceiveRadioStrength ( )
```

Get radio strength of data glove.

**Returns**

radio strength of data glove.

**5.3.3.13 Init()**

```
bool VRTRIX.VRTRIXDataWrapper.Init (
    HANDTYPE type )
```

Initialization method.



## Parameters

<i>type</i>	Data glove hand type.
-------------	-----------------------

## Returns

whether data glove is initialized successfully.

**5.3.3.14 InitDataGlove()**

```
static IntPtr VRTRIX.VRTRIXDataWrapper.InitDataGlove (
    bool AdvancedMode,
    GLOVEVERSION HardwareVersion )
```

Intialize the data glove and returns the interface pointer.

## Parameters

<i>AdvancedMode</i>	Unlock the yaw of fingers if set true
<i>HardwareVersion</i>	Specify the data glove hardware version

## Returns

The serial port object as IntPtr

**5.3.3.15 OnCloseFingerAlignment()** [1/2]

```
void VRTRIX.VRTRIXDataWrapper.OnCloseFingerAlignment (
    HANDTYPE type )
```

Align current gesture to finger close pose, used for calibration when advanced mode is activated.

## Parameters

<i>type</i>	Hand type of data glove
-------------	-------------------------

**5.3.3.16 OnCloseFingerAlignment()** [2/2]

```
static void VRTRIX.VRTRIXDataWrapper.OnCloseFingerAlignment (
    IntPtr sp )
```

Align the close finger pose

## Parameters

<i>sp</i>	The serial port object
-----------	------------------------

**5.3.3.17 OnOkPoseAlignment()**

```
static void VRTRIX.VRTRIXDataWrapper.OnOkPoseAlignment (
    IntPtr sp )
```

Align the OK finger pose

## Parameters

<i>sp</i>	The serial port object
-----------	------------------------

**5.3.3.18 OnSaveCalibration()**

```
static void VRTRIX.VRTRIXDataWrapper.OnSaveCalibration (
    IntPtr sp )
```

Save calibration result to hardware

## Parameters

<i>sp</i>	The serial port object
-----------	------------------------

**5.3.3.19 OpenPort()**

```
static bool VRTRIX.VRTRIXDataWrapper.OpenPort (
    IntPtr sp,
    int glove_id,
    HANDTYPE type )
```

Open the serial port

## Parameters

<i>sp</i>	The serial port object
<i>glove_id</i>	Data glove index id (from 0 - 15), if anything larger is set, then only one pair of glove is supported
<i>type</i>	Hand type.

**Returns**

Whether the port is opened successfully

**5.3.3.20 ReceivedDataCallback()**

```
delegate void VRTRIX.VRTRIXDataWrapper.ReceivedDataCallback (
    IntPtr pUserParam,
    IntPtr ptr,
    int data_rate,
    byte radio_strength,
    IntPtr cal_score_ptr,
    float battery,
    int hand_type,
    int radio_channel )
```

The delegate data receive function called inside unmanaged C++ API.

**Parameters**

<i>pUserParam</i>	Pointer of the user defined parameter which registered previously.
<i>ptr</i>	Array of the data received, where contains all joint rotation values.
<i>data_rate</i>	Data rate per second.
<i>radio_strength</i>	Radio transmission strength in dB
<i>cal_score_ptr</i>	Array of the calibration score received.
<i>battery</i>	Current battery level in percentage.
<i>hand_type</i>	The hand type of current hand pose.
<i>radio_channel</i>	Current radio channel used by wireless transmission.

**5.3.3.21 ReceivedEventCallback()**

```
delegate void VRTRIX.VRTRIXDataWrapper.ReceivedEventCallback (
    IntPtr pUserParam,
    IntPtr pEvent )
```

The delegate event receive function called inside unmanaged C++ API.

**Parameters**

<i>pUserParam</i>	Pointer of the user defined parameter which registered previously.
<i>pEvent</i>	Enum of current event received.

**5.3.3.22 RegisterDataCallback()**

```
static void VRTRIX.VRTRIXDataWrapper.RegisterDataCallback (
    IntPtr pUserParam,
    IntPtr sp,
    ReceivedDataCallback receivedDataCallback )
```

Register receiving and parsed frame calculation data callback

**Parameters**

<i>pUserParam</i>	User defined parameter/pointer passed into plugin interface, which will return in callback function.
<i>sp</i>	The serial port object
<i>receivedDataCallback</i>	received data callback.

**5.3.3.23 RegisterEventCallback()**

```
static void VRTRIX.VRTRIXDataWrapper.RegisterEventCallback (
    IntPtr sp,
    ReceivedEventCallback receivedEventCallback )
```

Register receiving hardware event callback

**Parameters**

<i>sp</i>	The serial port object
<i>receivedEventCallback</i>	received event callback.

**5.3.3.24 SetAdvancedMode() [1/2]**

```
void VRTRIX.VRTRIXDataWrapper.SetAdvancedMode (
    bool bIsAdvancedMode )
```

Activate advanced mode so that finger's yaw data will be unlocked.

**Parameters**

<i>bIsAdvancedMode</i>	Advanced mode will be activated if set to true.
------------------------	---

**5.3.3.25 SetAdvancedMode() [2/2]**

```
static void VRTRIX.VRTRIXDataWrapper.SetAdvancedMode (
```

```

    IntPtr sp,
    bool bIsAdvancedMode )

```

Set Advanced Mode.

#### Parameters

<i>sp</i>	The serial port object
<i>bIsAdvancedMode</i>	The boolean value to set

### 5.3.3.26 SetDistalThumbOffset()

```

static void VRTRIX.VRTRIXDataWrapper.SetDistalThumbOffset (
    IntPtr sp,
    double offset_x,
    double offset_y,
    double offset_z )

```

Set Distal Thumb Offset.

#### Parameters

<i>sp</i>	The serial port object
<i>offset_x</i>	x-axis offset to set
<i>offset_y</i>	y-axis offset to set
<i>offset_z</i>	z-axis offset to set

### 5.3.3.27 SetIntermediateThumbOffset()

```

static void VRTRIX.VRTRIXDataWrapper.SetIntermediateThumbOffset (
    IntPtr sp,
    double offset_x,
    double offset_y,
    double offset_z )

```

Set Intermediate Thumb Offset.

#### Parameters

<i>sp</i>	The serial port object
<i>offset_x</i>	x-axis offset to set
<i>offset_y</i>	y-axis offset to set
<i>offset_z</i>	z-axis offset to set

**5.3.3.28 SetProximalThumbOffset()**

```
static void VRTRIX.VRTRIXDataWrapper.SetProximalThumbOffset (
    IntPtr sp,
    double offset_x,
    double offset_y,
    double offset_z )
```

Set Proximal Thumb Offset.

**Parameters**

<i>sp</i>	The serial port object
<i>offset</i> ↔ <i>_x</i>	x-axis offset to set
<i>offset</i> ↔ <i>_y</i>	y-axis offset to set
<i>offset</i> ↔ <i>_z</i>	z-axis offset to set

**5.3.3.29 SetThumbOffset()**

```
void VRTRIX.VRTRIXDataWrapper.SetThumbOffset (
    Vector3 offset,
    VRTRIXBones joint )
```

Set thumb offset to counteract the difference between hands & gloves sensor installation.

**Parameters**

<i>offset</i>	Offset vector to set.
<i>joint</i>	the specific thumb joint to set.

**5.3.3.30 SetThumbSlerpRate() [1/2]**

```
void VRTRIX.VRTRIXDataWrapper.SetThumbSlerpRate (
    double slerp_proximal,
    double slerp_middle )
```

Set thumb slerp rate to counteract the difference between hands & gloves sensor installation.

**Parameters**

<i>slerp_proximal</i>	Proximal joint slerp rate to set.
<i>slerp_middle</i>	Middle joint slerp rate to set.

### 5.3.3.31 SetThumbSlerpRate() [2/2]

```
static void VRTRIX.VRTRIXDataWrapper.SetThumbSlerpRate (
    IntPtr sp,
    double slerp_proximal,
    double slerp_middle )
```

Set Thumb Slerp Rate.

#### Parameters

<i>sp</i>	The serial port object
<i>slerp_proximal</i>	thumb proximal joint slerp rate to set
<i>slerp_middle</i>	thumb middle joint slerp rate to set

### 5.3.3.32 StartStreaming()

```
static void VRTRIX.VRTRIXDataWrapper.StartStreaming (
    IntPtr sp )
```

Read the data from serial port asynchronously.

#### Parameters

<i>sp</i>	The serial port object
-----------	------------------------

#### Returns

Whether the read process successfully

### 5.3.3.33 VibratePeriod() [1/2]

```
void VRTRIX.VRTRIXDataWrapper.VibratePeriod (
    int msDurationMillisec )
```

Trigger a haptic vibration for a certain period.

#### Parameters

<i>msDurationMillisec</i>	vibration period
---------------------------	------------------



**5.3.3.34 VibratePeriod()** [2/2]

```
static void VRTRIX.VRTRIXDataWrapper.VibratePeriod (
    IntPtr sp,
    int msDurationMillisec )
```

Vibrate the data glove for given time period.

**Parameters**

<i>sp</i>	The serial port object
<i>msDurationMillisec</i>	Vibration duration in milliseconds


The documentation for this class was generated from the following file:

- VRTRIXBasicDataStreaming/VRTRIXDataWrapper.cs

**5.4 VRTRIX.VRTRIXGloveDataStreaming Class Reference**

[VRTRIX](#) Data Glove data streaming class.

Inheritance diagram for VRTRIX.VRTRIXGloveDataStreaming:

**Public Member Functions**

- void [OnConnectGlove](#) ()  
*Connect data glove and initialization.*
- void [OnDisconnectGlove](#) ()  
*Disconnect data glove and uninitialization.*
- void [OnHardwareCalibrate](#) ()  
*Save hardware calibration parameters in IMU, only used in magnetic field changed dramatically.*
- void [OnVibrate](#) ()  
*Trigger a haptic vibration on data glove.*
- void [OnChannelHopping](#) ()  
*Switch radio channel of data glove. Only used for testing/debugging. Automatic channel switching is enabled by default in normal mode.*
- void [SetAdvancedMode](#) (bool blsAdvancedMode)  
*Activate advanced mode so that finger's yaw data will be unlocked.*
- void [OnAlignFingers](#) ()

- Align five fingers to closed gesture (only if advanced mode is set to true). Also align wrist to the game object chosen.
- Quaternion [GetRotation](#) ([VRTRIXBones](#) bone)
  - Get current rotation of specific joint.
- int [GetCalScore](#) ([VRTRIXBones](#) bone)
  - Get current calibration score for specific IMU sensor.
- int [GetReceiveRadioStrength](#) ([HANDTYPE](#) type)
  - Get radio strength of data glove.
- int [GetReceiveRadioChannel](#) ([HANDTYPE](#) type)
  - Get current radio channel of data glove used.
- float [GetBatteryLevel](#) ([HANDTYPE](#) type)
  - Get current battery level in percentage of data glove.
- int [GetReceivedCalScoreMean](#) ([HANDTYPE](#) type)
  - Get current calibration score average value.
- int [GetReceivedDataRate](#) ([HANDTYPE](#) type)
  - Get data rate received per second.
- bool [GetGloveConnectionStat](#) ([HANDTYPE](#) type)
  - Get data glove connection status.
- [VRTRIXGloveStatus](#) [GetReceivedStatus](#) ([HANDTYPE](#) type)
  - Get data glove status.
- [VRTRIXGloveGesture](#) [GetGesture](#) ([HANDTYPE](#) type)
  - Get the gesture detected.

## Static Public Member Functions

- static GameObject [CheckDeviceModelName](#) ([HANDTYPE](#) type=[HANDTYPE.NONE](#), InteractiveDevice device=[InteractiveDevice.NONE](#))
  - Check the tracked device model name stored in hardware config to find specific hardware type. (SteamVR Tracking support)

## Public Attributes

- bool [IsVREnabled](#) = false
  - VR environment enable flag, set to true if run the demo in VR headset.
- GameObject [LH\\_ObjectToAlign](#)
  - If VR is NOT enabled, wrist joint need an object to align, which can be the camera, or parent joint of wrist(if a full body model is used), or can just be any other game objects.
- GameObject [RH\\_ObjectToAlign](#)
  - If VR is NOT enabled, wrist joint need an object to align, which can be the camera, or parent joint of wrist(if a full body model is used), or can just be any other game objects.
- Vector3 [RHTrackerOffset](#) = new Vector3(0.01f, 0, -0.035f)
  - If VR is enabled, HTC tracker is the default wrist tracking hardware, which is fixed to side part of data glove, this offset represents the offset between tracker origin to right wrist joint origin.
- Vector3 [LHTrackerOffset](#) = new Vector3(-0.01f, 0, -0.035f)
  - If VR is enabled, HTC tracker is the default wrist tracking hardware, which is fixed to side part of data glove, this offset represents the offset between tracker origin to left wrist joint origin.
- [GLOVEVERSION](#) version
  - Hardware version of [VRTRIX](#) data gloves, currently DK1, DK2 and PRO are supported.
- bool [IsEnableMultipleGloves](#)
  - Mutiple gloves enable flag, set to true if run multiple gloves on the same PC.
- [GloveIndex](#) Index

- If mutiple gloves mode is enbaled, specify different index for different pair of gloves. Otherwise, just select None.*
- Vector3 [ql\\_modeloffset](#)  
*Model mapping parameters for left hand, only used when finger joint axis definition is different from wrist joint, otherwise, just set to 0,0,0.*
  - Vector3 [qr\\_modeloffset](#)  
*Model mapping parameters for right hand, only used when finger joint axis definition is different from wrist joint, otherwise, just set to 0,0,0.*
  - Vector3[] [ql\\_axisoffset](#) = new Vector3[3]  
*Model mapping parameters for left hand, only used when wrist joint axis definition is different from hardware wrist joint, otherwise, just set to identity matrix {(1,0,0),(0,1,0),(0,0,1)}. Please read the sdk tutorial documentation to learn how to set this parameter properly.*
  - Vector3[] [qr\\_axisoffset](#) = new Vector3[3]  
*Model mapping parameters for right hand, only used when wrist joint axis definition is different from hardware wrist joint, otherwise, just set to identity matrix {(1,0,0),(0,1,0),(0,0,1)}. Please read the sdk tutorial documentation to learn how to set this parameter properly.*
  - Vector3[] [thumb\\_offset](#) = new Vector3[3]  
*Model mapping parameters for thumb joint, used to tune thumb offset between the model and hardware sensor placement. Please read the sdk tutorial documentation to learn how to set this parameter properly.*
  - double [thumb\\_proximal\\_slerp](#)  
*Model mapping parameters for thumb proximal joint, used to tune thumb slerp algorithm parameter. Please read the sdk tutorial documentation to learn how to set this parameter properly.*
  - double [thumb\\_middle\\_slerp](#)  
*Model mapping parameters for thumb middle joint, used to tune thumb slerp algorithm parameter. Please read the sdk tutorial documentation to learn how to set this parameter properly.*
  - [VRTRIXDataWrapper](#) LH

### 5.4.1 Detailed Description

[VRTRIX](#) Data Glove data streaming class.

A basic data streaming class for demonstration.

### 5.4.2 Member Function Documentation

#### 5.4.2.1 CheckDeviceModelName()

```
static GameObject VRTRIX.VRTRIXGloveDataStreaming.CheckDeviceModelName (
    HANDTYPE type = HANDTYPE.NONE,
    InteractiveDevice device = InteractiveDevice.NONE ) [static]
```

Check the tracked device model name stored in hardware config to find specific hardware type. (SteamVR Tracking support)

Parameters

<i>type</i>	Hand type to check(if wrist tracker for data glove is the hardware to check).
<i>device</i>	Device type to check(if other kind of interactive hardware to check).

**Returns**

the gameobject of the tracked device.

**5.4.2.2 GetBatteryLevel()**

```
float VRTRIX.VRTRIXGloveDataStreaming.GetBatteryLevel (
    HANDTYPE type )
```

Get current battery level in percentage of data glove.

**Parameters**

<i>type</i>	Data glove hand type.
-------------	-----------------------

**Returns**

current battery level in percentage of data glove.

**5.4.2.3 GetCalScore()**

```
int VRTRIX.VRTRIXGloveDataStreaming.GetCalScore (
    VRTRIXBones bone )
```

Get current calibration score for specific IMU sensor.

**Parameters**

<i>bone</i>	specific joint of hand.
-------------	-------------------------

**Returns**

current calibration score for specific IMU sensor. Lower value of score means better calibration performance.

**5.4.2.4 GetGesture()**

```
VRTRIXGloveGesture VRTRIX.VRTRIXGloveDataStreaming.GetGesture (
    HANDTYPE type )
```

Get the gesture detected.

**Parameters**

<i>type</i>	Data glove hand type.
-------------	-----------------------

**Returns**

the gesture detected.

**5.4.2.5 GetGloveConnectionStat()**

```
bool VRTRIX.VRTRIXGloveDataStreaming.GetGloveConnectionStat (
    HANDTYPE type )
```

Get data glove connection status.

**Parameters**

<i>type</i>	Data glove hand type.
-------------	-----------------------

**Returns**

data glove connection status.

**5.4.2.6 GetReceivedCalScoreMean()**

```
int VRTRIX.VRTRIXGloveDataStreaming.GetReceivedCalScoreMean (
    HANDTYPE type )
```

Get current calibration score average value.

**Parameters**

<i>type</i>	Data glove hand type.
-------------	-----------------------

**Returns**

current calibration score average value.

#### 5.4.2.7 GetReceivedDataRate()

```
int VRTRIX.VRTRIXGloveDataStreaming.GetReceivedDataRate (
    HANDTYPE type )
```

Get data rate received per second.

##### Parameters

<i>type</i>	Data glove hand type.
-------------	-----------------------

##### Returns

data rate received per second.

#### 5.4.2.8 GetReceivedStatus()

```
VRTRIXGloveStatus VRTRIX.VRTRIXGloveDataStreaming.GetReceivedStatus (
    HANDTYPE type )
```

Get data glove status.

##### Parameters

<i>type</i>	Data glove hand type.
-------------	-----------------------

##### Returns

data glove status.

#### 5.4.2.9 GetReceiveRadioChannel()

```
int VRTRIX.VRTRIXGloveDataStreaming.GetReceiveRadioChannel (
    HANDTYPE type )
```

Get current radio channel of data glove used.

##### Parameters

<i>type</i>	Data glove hand type.
-------------	-----------------------

**Returns**

current radio channel of data glove used.

**5.4.2.10 GetReceiveRadioStrength()**

```
int VRTRIX.VRTRIXGloveDataStreaming.GetReceiveRadioStrength (
    HANDTYPE type )
```

Get radio strength of data glove.

**Parameters**

<i>type</i>	Data glove hand type.
-------------	-----------------------

**Returns**

radio strength of data glove. Higher value of score means better radio strength.

**5.4.2.11 GetRotation()**

```
Quaternion VRTRIX.VRTRIXGloveDataStreaming.GetRotation (
    VRTRIXBones bone )
```

Get current rotation of specific joint.

**Parameters**

<i>bone</i>	specific joint of hand.
-------------	-------------------------

**Returns**

current rotation of specific joint.

**5.4.2.12 SetAdvancedMode()**

```
void VRTRIX.VRTRIXGloveDataStreaming.SetAdvancedMode (
    bool bIsAdvancedMode )
```

Activate advanced mode so that finger's yaw data will be unlocked.

**Parameters**

<i>blsAdvancedMode</i>	Advanced mode will be activated if set to true.
------------------------	---

The documentation for this class was generated from the following file:

- VRTRIXBasicDataStreaming/VRTRIXGloveDataStreaming.cs

## 5.5 VRTRIX.VRTRIXUtilities Class Reference

Bone utility functions class.

### Static Public Member Functions

- static string [GetBoneName](#) (int id)  
*Get current bone name for specific bone ID.*
- static int [GetBoneIndex](#) (string name)  
*Get current bone index for specific bone name.*

### 5.5.1 Detailed Description

Bone utility functions class.

### 5.5.2 Member Function Documentation

#### 5.5.2.1 GetBoneIndex()

```
static int VRTRIX.VRTRIXUtilities.GetBoneIndex (
    string name ) [static]
```

Get current bone index for specific bone name.

**Parameters**

<i>name</i>	Bone name.
-------------	------------

**Returns**

current bone index for specific bone name.



### 5.5.2.2 GetBoneName()

```
static string VRTRIX.VRTRIXUtilities.GetBoneName (
    int id ) [static]
```

Get current bone name for specific bone ID.

#### Parameters

<i>id</i>	id of bone.
-----------	-------------

#### Returns

current bone name for specific bone ID.

The documentation for this class was generated from the following file:

- VRTRIXBasicDataStreaming/VRTRIXUtilities.cs



# Index

- ChannelHopping
  - VRTRIX.VRTRIXDataWrapper, [15](#)
- CheckDeviceModelName
  - VRTRIX.VRTRIXGloveDataStreaming, [29](#)
- ClosePort
  - VRTRIX.VRTRIXDataWrapper, [15](#)
- GetBatteryLevel
  - VRTRIX.VRTRIXGloveDataStreaming, [30](#)
- GetBoneIndex
  - VRTRIX.VRTRIXUtilities, [34](#)
- GetBoneName
  - VRTRIX.VRTRIXUtilities, [34](#)
- GetCalScore
  - VRTRIX.VRTRIXGloveDataStreaming, [30](#)
- GetGesture
  - VRTRIX.VRTRIXGloveDataStreaming, [30](#)
- GetGloveConnectionStat
  - VRTRIX.VRTRIXGloveDataStreaming, [31](#)
- GetReceiveBattery
  - VRTRIX.VRTRIXDataWrapper, [16](#)
- GetReceivedCalScore
  - VRTRIX.VRTRIXDataWrapper, [16](#)
- GetReceivedCalScoreMean
  - VRTRIX.VRTRIXDataWrapper, [16](#)
  - VRTRIX.VRTRIXGloveDataStreaming, [31](#)
- GetReceivedDataRate
  - VRTRIX.VRTRIXDataWrapper, [17](#)
  - VRTRIX.VRTRIXGloveDataStreaming, [31](#)
- GetReceivedGestureAngle
  - VRTRIX.VRTRIXDataWrapper, [17](#)
- GetReceivedRotation
  - VRTRIX.VRTRIXDataWrapper, [17](#)
- GetReceivedStatus
  - VRTRIX.VRTRIXDataWrapper, [18](#)
  - VRTRIX.VRTRIXGloveDataStreaming, [32](#)
- GetReceiveRadioChannel
  - VRTRIX.VRTRIXDataWrapper, [18](#)
  - VRTRIX.VRTRIXGloveDataStreaming, [32](#)
- GetReceiveRadioStrength
  - VRTRIX.VRTRIXDataWrapper, [18](#)
  - VRTRIX.VRTRIXGloveDataStreaming, [33](#)
- GetRotation
  - VRTRIX.VRTRIXGloveDataStreaming, [33](#)
- GloveIndex
  - VRTRIX, [8](#)
- GLOVEVERSION
  - VRTRIX, [8](#)
- HANDTYPE
  - VRTRIX, [8](#)
- VRTRIX, [8](#)
- Init
  - VRTRIX.VRTRIXDataWrapper, [18](#)
- InitDataGlove
  - VRTRIX.VRTRIXDataWrapper, [19](#)
- MapToVRTRIX\_BoneName
  - VRTRIXBoneMapping, [12](#)
- OnCloseFingerAlignment
  - VRTRIX.VRTRIXDataWrapper, [19](#)
- OnOkPoseAlignment
  - VRTRIX.VRTRIXDataWrapper, [21](#)
- OnSaveCalibration
  - VRTRIX.VRTRIXDataWrapper, [21](#)
- OpenPort
  - VRTRIX.VRTRIXDataWrapper, [21](#)
- ReceivedDataCallback
  - VRTRIX.VRTRIXDataWrapper, [22](#)
- ReceivedEventCallback
  - VRTRIX.VRTRIXDataWrapper, [22](#)
- RegisterDataCallback
  - VRTRIX.VRTRIXDataWrapper, [22](#)
- RegisterEventCallback
  - VRTRIX.VRTRIXDataWrapper, [23](#)
- SetAdvancedMode
  - VRTRIX.VRTRIXDataWrapper, [23](#)
  - VRTRIX.VRTRIXGloveDataStreaming, [33](#)
- SetDistalThumbOffset
  - VRTRIX.VRTRIXDataWrapper, [24](#)
- SetIntermediateThumbOffset
  - VRTRIX.VRTRIXDataWrapper, [24](#)
- SetProximalThumbOffset
  - VRTRIX.VRTRIXDataWrapper, [25](#)
- SetThumbOffset
  - VRTRIX.VRTRIXDataWrapper, [25](#)
- SetThumbSlerpRate
  - VRTRIX.VRTRIXDataWrapper, [25](#), [26](#)
- StartStreaming
  - VRTRIX.VRTRIXDataWrapper, [26](#)
- VibratePeriod
  - VRTRIX.VRTRIXDataWrapper, [26](#), [27](#)
- VRTRIX, [7](#)
  - GloveIndex, [8](#)
  - GLOVEVERSION, [8](#)
  - HANDTYPE, [8](#)
  - VRTRIXBones, [8](#)

- VRTRIXGloveEvent, [8](#)
- VRTRIXGloveStatus, [9](#)
- VRTRIX.VRTRIXDataWrapper, [12](#)
  - ChannelHopping, [15](#)
  - ClosePort, [15](#)
  - GetReceiveBattery, [16](#)
  - GetReceivedCalScore, [16](#)
  - GetReceivedCalScoreMean, [16](#)
  - GetReceivedDataRate, [17](#)
  - GetReceivedGestureAngle, [17](#)
  - GetReceivedRotation, [17](#)
  - GetReceivedStatus, [18](#)
  - GetReceiveRadioChannel, [18](#)
  - GetReceiveRadioStrength, [18](#)
  - Init, [18](#)
  - InitDataGlove, [19](#)
  - OnCloseFingerAlignment, [19](#)
  - OnOkPoseAlignment, [21](#)
  - OnSaveCalibration, [21](#)
  - OpenPort, [21](#)
  - ReceivedDataCallback, [22](#)
  - ReceivedEventCallback, [22](#)
  - RegisterDataCallback, [22](#)
  - RegisterEventCallback, [23](#)
  - SetAdvancedMode, [23](#)
  - SetDistalThumbOffset, [24](#)
  - SetIntermediateThumbOffset, [24](#)
  - SetProximalThumbOffset, [25](#)
  - SetThumbOffset, [25](#)
  - SetThumbSlerpRate, [25](#), [26](#)
  - StartStreaming, [26](#)
  - VibratePeriod, [26](#), [27](#)
  - VRTRIXDataWrapper, [15](#)
- VRTRIX.VRTRIXDataWrapper.VRTRIX\_Quat, [11](#)
- VRTRIX.VRTRIXGloveDataStreaming, [27](#)
  - CheckDeviceModelName, [29](#)
  - GetBatteryLevel, [30](#)
  - GetCalScore, [30](#)
  - GetGesture, [30](#)
  - GetGloveConnectionStat, [31](#)
  - GetReceivedCalScoreMean, [31](#)
  - GetReceivedDataRate, [31](#)
  - GetReceivedStatus, [32](#)
  - GetReceiveRadioChannel, [32](#)
  - GetReceiveRadioStrength, [33](#)
  - GetRotation, [33](#)
  - SetAdvancedMode, [33](#)
- VRTRIX.VRTRIXUtilities, [34](#)
  - GetBoneIndex, [34](#)
  - GetBoneName, [34](#)
- VRTRIXBoneMapping, [11](#)
  - MapToVRTRIX\_BoneName, [12](#)
- VRTRIXBones
  - VRTRIX, [8](#)
- VRTRIXDataWrapper
  - VRTRIX.VRTRIXDataWrapper, [15](#)
- VRTRIXGloveEvent
  - VRTRIX, [8](#)
- VRTRIXGloveStatus
  - VRTRIX, [9](#)